



Guidelines for CABBAGE

Pre-plant Soil Application: Apply *Soil Solution* @ 24 Oz/acre. This application should be made in the Fall and incorporated, or up to planting in the Spring. For No-till or over a growing crop, increase rate to 32 Oz/acre.

Hopper Box Seed Treatment: Apply *Seed Coat* @ 2 Oz (dry weight) per planted acre of seed.

Transplant Water: Apply *PercPlus* @ 8 Oz/acre in with total water volume.

Planting: Knifed into side of seed bed (6X6): Apply *PercPlus* @ 16 Oz/acre, *Sulfur Plus* @ 32 Oz/acre and *Boron Plus* @ 20 Oz/acre in a minimum 10 gallon total volume.

Note: This application can replace the Transplant water application.

Seedling Foliar: After initial shock of transplant (4 to 5 days). Apply *PercPlus* @ 16 Oz/acre, *Zinc Plus* @ 8 Oz/acre, and *Boron Plus* @ 4 Oz/acre. Apply twice on seven day intervals.

Zinc Plus will provide additional Zinc and Sulfur.

NOTE: *Zinc Plus* may be replaced with *MicroVite* @ 16 Oz/acre.

Prior to Maturity: Multiple Applications: Foliar apply *CropKarb* @ 32 Oz/acre on weekly intervals for three to four applications. **NOTE:** Add *Calcium Plus* @ 32 oz/acre to this combination in the final application just prior to harvest.

NOTE: *CropKarb* may be replaced with a tank-mix of *Potassium Plus* @ 32 Oz, *PercPlus* @ 8 to 16 Oz, and *Boron Plus* @ 4 Oz. *Plant Power* may be substituted for *PercPlus* and vice-versa in any application and at the same rate.

Mixing: Always dilute *Potassium Plus* in water first, and follow with other ingredients in listed order to avoid excessive foaming.

These **DeltAg Guidelines** have been utilized to improve overall crop health and are not intended to be utilized as a replacement for basic and customary fertilizer applications. **“Other Crop Specific Guidelines are available upon request.”**