



Guidelines for PEANUTS

Pre-plant Soil Application: Apply *Soil Solution* @ 24 Oz/acre. This application should be made in the Fall and incorporated, or up to planting in the Spring. For No-till or over a growing crop, increase rate to 32 Oz/acre.

At Planting:

Hopper Box: Apply *Seed Coat* @ 2 to 3 Oz (dry weight)/acre.

Soil: Option # 1: In-Furrow apply *PercPlus* @ 8 Oz and *Calcium Plus* @ 16 Oz/acre.

Option # 2: Knifed into Seed Bed Early: (6 x 6) Apply *PercPlus* @ 16 Oz/acre, *Boron Plus* @ 8 Oz/acre & *Calcium Plus* at 32 Oz/acre.

Seedling Foliar: (28 Days after Planting); Apply foliar *PercPlus* @ 24 Oz/acre. (May be applied w Fungicide)

NOTE: Add *Calcium Plus* @ 32 Oz/acre with *Boron Plus* @ 4 Oz/acre to this application if not applied in Option #1 or #2 above.

Initial Pegging: (42 Days after Planting); Foliar *Calcium Plus* @ 32 Oz/acre, *Manganese Plus* @ 16 Oz/acre and *PercPlus* @ 12 Oz/acre.

Pegging + 14 Days: (58 Days after planting); Repeat **Initial Pegging** treatment above.

Initial Bulking: (35-42 Days after Pegging); Apply foliar *CropKarb* @ 32 Oz/acre.

Sizing-Bulking: (49-56 Days after Pegging); Apply foliar *CropKarb* @ 32 Oz/acre.

NOTE: *CropKarb* may be replaced with a tank-mix of *Potassium Plus* @ 32 Oz, *PercPlus* @ 8 to 16 Oz, and *Boron Plus* @ 4 Oz. *Plant Power* may be substituted for *PercPlus* and vice-versa in any application and at the same rate.

Mixing: Always dilute *Potassium Plus* in water first, and follow with other ingredients in listed order to avoid excessive foaming.

These **DeltAg Guidelines** have been utilized to improve overall crop health and are not intended to be utilized as a replacement for basic and customary fertilizer applications. **“Other Crop Specific Guidelines are available upon request.”**